

Template

webconfig.ini

```
#
*****
# MapGuide Web Configuration File
#
# WARNING: BE VERY CAREFUL WHEN MODIFYING THIS FILE AS IT COULD
# ADVERSLY IMPACT SERVER PERFORMANCE
#
*****
# COMMON VALIDATION INFORMATION
#
# (Unless otherwise noted under the property description)
# -----
# String Property                                Range of String Length    Reserved
# Characters
# -----
# File Name                                0 < Length <= 128        \/:*?"<>|
# Folder Name                             0 < Length <= 128        \/:*?"<>|
# Log Parameters                           0 <= Length <= 1024
# Password                                0 <= Length <= 64        \t\r\n\v\f
# Path                                    0 < Length <= 255        *?"<>|
# -----
# Numeric Property                                Range of Numeric Value
# -----
# Port Number                                0 <= Value <= 65535
#
*****

[GeneralProperties]
#
*****
# G E N E R A L
#
# Property Name                                Description
# -----
# DefaultMessageLocale                        ISO 639-1 name for the message
# locale
#                                             Length = 2
```

```
# Example: en
# or
# Length = 5
# Example: en-US
#
# WARNING: if a 5 character locale is
specified
# the first 2 characters must
be lower
# case and the last 2
characters must
# be upper case.
#
# LogsPath Path where log files are stored
# MentorDictionaryPath The path where the CS-Map Coordinate
System Dictionaries are installed
# ResourcesPath Path where the localization resource
files are stored
# TcpIpMtu The TCP/IP maximum transmission unit
# 0 < Value <= 65535
# TempPath Path where the temporary files are
stored
# FailoverRetryTime Time in seconds for when to retry
connecting
# to a MapGuide server that has gone
offline.
# Note: For a single Web Tier and
MapGuide server
# pair use 1. For a load
balanced
# configuration with multiple
# MapGuide servers use 60. Values other
# than 1 will
# cause a delay when re-
# establishing a
# connection with the Web Tier
# after
# restarting a MapGuide server.
#
#
*****
*****
DefaultMessageLocale = en
LogsPath = Logs/
MentorDictionaryPath =C:\Program Files\OSGeo\MapGuide\CS-
Map\Dictionaries\
ResourcesPath =C:\Program
Files\OSGeo\MapGuide\Web\www\mapagent\Resources
TcpIpMtu = 1460
TempPath =C:\Program
```

```
Files\OSGeo\MapGuide\Web\Temp\
FailoverRetryTime                = 1

[AdministrativeConnectionProperties]
#
*****
*****
# ADMINISTRATIVE CONNECTION
#
# Property Name                    Description
# -----
#
# MaxConnections                  The maximum allowed concurrent
connections for this port.
#                                Default value of 2 is for a typical
load when the web
#                                is connected to a quad core server
machine.
#
# Port                           The port to use for administration
operations
#
#                                WARNING: If you change the port #
here you
#                                must also change the
corresponding
#                                port # for the server
configuration
#                                file.
#
#
*****
*****
MaxConnections                    = 2
Port                             =2810

[ClientConnectionProperties]
#
*****
*****
# CLIENT CONNECTION
#
# Property Name                    Description
# -----
#
# MaxConnections                  The maximum allowed concurrent
connections for this port.
#                                Default value of 12 is for a typical
load when the web
#                                is connected to a quad core server
machine.
```

```
#
# Port                                The port to use for client
operations
#
#                                WARNING: If you change the port #
here you
#                                must also change the
corresponding
#                                port # for the server
configuration
#                                file.
#
#
*****
*****
MaxConnections                        = 12
Port                                =2811

[SiteConnectionProperties]
#
*****
*****
# S I T E   C O N N E C T I O N
#
# Property Name                      Description
# -----
#
# IpAddress                          The IP address of the site server
#                                0 < Length <= 255
#
# MaxConnections                     The maximum allowed concurrent
connections for this port.
#                                Default value of 6 is for a typical
load when the web
#                                is connected to a quad core server
machine.
#
# Port                               The port to use for site operations
#
#                                WARNING: If you change the port #
here you
#                                must also change the
corresponding
#                                port # for the server
configuration
#                                file.
#
#
*****
*****
IpAddress                            =127.0.0.1
```

```
MaxConnections          = 6
Port                    =2812

[AgentProperties]
#
*****
*****
# M A P   A G E N T
#
# Property Name          Description
# -----
#
# DebugPause            Number of seconds the agent pauses
before
#
#                       each request, for debugging purpose
#                       0 <= Value <= 86400
# DisableAuthoring      Disables Authoring HTTP requests
#                       0 = false and 1 = true
# DisableWfs            Disables OGC Wfs HTTP requests
#                       0 = false and 1 = true
# DisableWms            Disables OGC Wms HTTP requests
#                       0 = false and 1 = true
# ErrorLogEnabled        0 = log disabled, 1 = log enabled
# ErrorLogFilename       Name of the log file
# RequestLogEnabled      0 = log disabled, 1 = log enabled
# RequestLogFilename     Name of the log file
#
*****
*****
DebugPause              = 0
DisableAuthoring        = 0
DisableWfs              = 0
DisableWms              = 0
ErrorLogEnabled          = 0
ErrorLogFilename        = Error.log
RequestLogEnabled        = 0
RequestLogFilename      = Request.log

[OgcProperties]
#
*****
*****
# O G C   S E T T I N G S
#
# Property Name          Description
# -----
#
# WfsPassword            Password to be used for credentials
in WFS
#
#                       requests
# WmsPassword            Password to be used for credentials
```

```
in WMS
#
# CITEWfsEnabled
#
HTTP requests
#
#
# CITEWmsEnabled
#
HTTP requests
#
#
*****
*****
WfsPassword           = wfs
WmsPassword           = wms
CITEWfsEnabled        = 0
CITEWmsEnabled        = 0

[WebApplicationProperties]
#
*****
*****
# W E B    A P P L I C A T I O N    S E T T I N G S
#
# Property Name          Description
# -----
#
# TemplateRootFolder    The root folder containing the
viewer
#
# WidgetInfoFolder      The folder containing widget info
files
# ContainerInfoFolder    The folder containing container info
files
#
*****
*****
TemplateRootFolder      =C:\Program
Files\OSGeo\MapGuide\Web\www\fusion\templates\mapguide
WidgetInfoFolder        =C:\Program
Files\OSGeo\MapGuide\Web\www\fusion\widgets\widgetinfo
ContainerInfoFolder      =C:\Program
Files\OSGeo\MapGuide\Web\www\fusion\containerinfo
```

From:

<https://wiki.geowebframework.com/> - **GeowebFramework**

Permanent link:

https://wiki.geowebframework.com/doku.php?id=gwusermanual:webconfig_ini

Last update: **2022/11/24 18:10**

